


fortigate, vpn, sede

Conexión de sedes mediante una VPN

Vamos a realizar una conexión entre sedes, teniendo en cada sede un equipo fortigate. Para ello tenemos que crear una conexión VPN en cada sede.

Creamos la VPN en la sede central


Utilizamos el asistente para realizar la configuración. Para ello vamos al menú de la izquierda y seleccionamos VPN→IPsec→Wizard y seleccionamos la opción Site to Site - FortiGate



Definimos en remote gateway la ip pública del equipo al que vamos a conectarnos, la interfaz de salida por la que vamos a conectar y el tipo de autenticación que vamos a usar en ambos extremos.




En caso de usar la autenticación mediante clave precompartida, usar una contraseña segura



The screenshot shows the 'Authentication' step of the FortiGate VPN Setup wizard. At the top, there are three tabs: 'VPN Setup' (checked), 'Authentication' (active), and 'Policy & Routing'. Below the tabs is a title bar that reads 'vpn a central : Site to Site - FortiGate'. The main configuration area includes: 'Remote Gateway' with a text input field containing 'ip pública equipo remoto'; 'Outgoing Interface' with a dropdown menu showing 'WAN 1'; 'Authentication Method' with radio buttons for 'Pre-shared Key' (selected) and 'Signature'; 'Pre-shared Key' with a text input field containing ten dots and a cursor, and a checked checkbox for 'Hide Characters'. At the bottom, there are three buttons: '< Back', 'Next >', and 'Cancel'.

Definimos el interfaz de entrada de la red local, el direccionamiento ip de la red local y el de la la red remota



The screenshot shows the 'Policy & Routing' step of the FortiGate VPN Setup wizard. At the top, there are three tabs: 'VPN Setup' (checked), 'Authentication' (checked), and 'Policy & Routing' (active). Below the tabs is a title bar that reads 'fgdg : Site to Site - FortiGate'. The main configuration area includes: 'Local Interface' with a dropdown menu; 'Local Subnets' with a text input field and a question mark icon; and 'Remote Subnets' with a text input field and a question mark icon. At the bottom, there are three buttons: '< Back', 'Create', and 'Cancel'.

Al finalizar el asistente nos creará las políticas, las rutas, los grupos y objetos necesarios.

Creamos la VPN en la sede

Seguimos los mismo pasos que cuando creamos la VPN en la sede central, pero cambiando los parámetros del gateway remoto, puerto, etc con los nuevos valores .

VPN Setup > **2 Authentication** > 3 Policy & Routing

vpn a central : Site to Site - FortiGate

Remote Gateway

Outgoing Interface

Authentication Method ☒ Pre-shared Key ☐ Signature

Pre-shared Key

☒ Hide Characters

< Back Next > Cancel

VPN Setup > Authentication > **3 Policy & Routing**

fgdg : Site to Site - FortiGate

Local Interface

Local Subnets

Remote Subnets

< Back Create Cancel

From:
<https://intrusos.info/> - LCWIKI

Permanent link:
<https://intrusos.info/doku.php?id=hardware:fortigate:conectarsede&rev=1528710892>

Last update: 2023/01/18 14:15

