


Vcenter Operation Manager

El vcenter operation managers es un appliance que se distribute en formato ovf y que podemos desplegar en nuestra infraestructura para obtener datos de salud y rendimiento de la misma.

Para su instalación necesitamos disponer de un cluster con DRS y de un pool de ip previamente a despligue creamos el ip pool de la siguiente manera. Desde nuestro webclient



The screenshot shows the 'vcenter operation manager - Edit Network Protocol Profile' window. The 'Select name and network' tab is active. The 'Name' field is set to 'vcenter operation manager'. The 'Network association' list shows several options, with 'VL_PRO (already associated with vcenter operation manager)' selected. The 'OK' and 'Cancel' buttons are at the bottom right.


The screenshot shows the 'vcenter operation manager - Edit Network Protocol Profile' window, now on the 'Configure IPv4' tab. The 'Subnet' field is highlighted with a red box and contains '10.10.10.0'. The 'Subnet mask' is '255.255.255.0'. The 'Address range' field is highlighted with a red box and contains '10.10.10.10'. The 'Gateway' field is highlighted with a red box and contains '10.10.10.1'. The 'DHCP present' checkbox is unchecked. The 'DNS server addresses' field is highlighted with a red box and contains '10.10.10.10'. The 'Enable IP pool' checkbox is unchecked. The 'IP pool range' field is highlighted with a red box and contains 'No marcar'. A red arrow points from the 'No marcar' text to the 'Enable IP pool' checkbox. The 'View range' button is visible next to the 'IP pool range' field. The 'OK' and 'Cancel' buttons are at the bottom right.




No marcar la casilla de activar el pool

Una vez creado el ip pool, procedemos a desplegar el appliance. Aceptamos la licencia y en mi caso les puse una dirección ip fija.

Una vez desplegado el appliance tenemos que arrancar las dos MV que crea, y proceder a terminar de configurar el Vcenter Operation Manager bien desde https://ip_vcenteroperation/admin/ o desde el icono que se crea en el vcenter



Nos validamos en el vCenter Operations Manager la primera vez con usuario y clave → **admin** y lo terminamos de configurar cambiando las contraseñas e indicando la dirección de nuestro vcenter standard





el usuario root trae como clave por defecto vmware

From:
<https://intrusos.info/> - LCWIKI

Permanent link:
<https://intrusos.info/doku.php?id=virtualizacion:vmware:version5:vcenteroperation&rev=1403263361>

Last update: **2023/01/18 14:41**

